



WsN-Viewer

Quick Installation Guide

WsN-Viewer – Quick Installation Guide

System requirements

The **WsN-Viewer** may be installed on

- Windows 10, Release 1809 (Build 17763) or later,

- Windows 11

- Windows Server 2019 and 2022

The **WsN-Viewer** supports the following CPUs:

- x64, x86 and Arm64

WsN-Viewer – Quick Installation Guide

System preparation: App-Installer

The **WsN-Viewer** will be installed by Microsoft's "*App Installer*".



"*App Installer*" needs correct Windows-settings **once and before** **WsN-Viewer** installation.

Setting: Choose where to get the app (actual Windows 10/11 Server 2022)

Setting: Select “Sideload apps” (older Windows 10 Windows Server 2019)


WsN-Viewer – Quick Installation Guide

System Preparation: Choose where to get apps

Actual Windows 10 and Server 2022

Select Settings => Apps


Set “Choose where to get apps” to “Anywhere”



Actual Windows 11

Select Settings => Apps => Advanced app settings"

Set “Choose where to get apps” to “Anywhere”




WsN-Viewer – Quick Installation Guide

System-Preparation: Sideload apps

Older Windows 10 / Windows Server 2019

Select “Settings => Update & Security => For developers”

“Sideload apps” must be enabled



WsN-Viewer – Quick Installation Guide

System preparation: Webview2 runtime

The **WsN-Viewer** needs the *Microsoft Edge Webview2 runtime library* pre-installed!

Click on the link, download and install *WebView2 runtime* once.

<https://go.microsoft.com/fwlink/?LinkId=2124703>

WsN-Viewer – Quick Installation Guide


Download

- Go to the official web site <https://workshop-net.net/en/viewer>
- Click on “Download”

The new **WsN-Viewer** is your **cost free** solution, to view and print all XML-results of your Workshop- and Testequip with your company logo and company address.

As an **attractive added value**, the **WsN-Viewer** offers, among other things, the possibility to query the complete p background and do **not require administrative rights** for installation!

Installation



[Download](#)

[Details](#)

[Manual](#)

The **WsN-Viewer** may be installed on


- Windows 10, Release 1809 (Build 17763) oder later
- Windows 11
- Windows Server 2019 and 2022

and supports x64-, x86 and Arm64 processors!

WsN-Viewer – Quick Installation Guide

Installation on Windows 10/11 (Desktop)

- Double click „WsNViewer (Package).appinstaller“ to run App-Installer
- Follow the instructions



If the App-Installer does not start, check


- Wrong File Association
- App-Installer Missing

WsN-Viewer – Quick Installation Guide

Installation on Windows Server or from command line

- Open PowerShell, change directory to your Download folder
- Execute (Copy&Paste)

```
Add-AppxPackage -AppInstallerFile "WsNViewer (Package).appinstaller"
```



The screenshot shows two overlapping Windows PowerShell windows. Both windows are titled 'Administrator: Windows PowerShell' and show the same command being run:

```
Administrator: Windows PowerShell
Windows PowerShell
Copyright (C) Microsoft Corporation. All rights reserved.

Install the latest PowerShell for new features and improvements! https://aka.ms/PSWindows

PS C:\Users\Administrator> cd .\Downloads\
PS C:\Users\Administrator\Downloads> Add-AppxPackage -AppInstallerFile ".\WsNViewer (Package).appinstaller"
PS C:\Users\Administrator\Downloads>
```

The second window is partially visible behind the first. It shows the deployment progress:

```
Administrator: Windows PowerShell
Windows PowerShell
Copyright (C) Microsoft Corporation. All rights reserved.

Deployment operation progress: C:\Users\Administrator\Downloads\WsNViewer (Package).appinstaller
Processing
[oooooooooooo]
```

Hint:


If the deployment fails, please check [Deployment failed](#)

WsN-Viewer – Quick Installation Guide


Start

Start the **WsN-Viewer** via start menu

If you get this, the installation is completed



If You get this, [WebView runtime missing](#)




Hint:

Please contact Your DMS-supplier, if You want to run the **WsN-Viewer** directly from Your DMS!

WsN-Viewer – Quick Installation Guide

Installation issue: Missing WebView2 runtime

Issue: *WebView2 runtime* is missing, you see this screen after the start



Solution:

Click on the link, download and install *WebView2 runtime* once.

<https://go.microsoft.com/fwlink/?LinkId=2124703>

WsN-Viewer – Quick Installation Guide

Installation issue: Deployment failed

Issue: Deployment failed with HRESULT: 0x80073CFF

This error message is displayed inside “App Installer” or on the command line


Solution:

- You need a sideloading-enabled system!
- See: [System-Preparation: Sideload apps](#)

WsN-Viewer – Quick Installation Guide

Installation issue: Wrong File Association

Issue: File association to .appinstaller is missing or wrong,
f.e. Windows offers the “Windows Notepad” for installation.




WsN-Viewer – Quick Installation Guide

Installation issue: Wrong File Association

Solution 1:

- Save the .appinstaller file in your downloads folder
- Right click and select “open with”
- Choose “another app”
- Select “App-Installer”, if missing see next page!
- Windows 11: Click “Always”
- Windows 10: Set the check box
“Always use this app to open .appinstaller files”
and click OK



Solution 2:

- Use the [command line installation](#)

WsN-Viewer – Quick Installation Guide

Installation issue: App-Installer missing

The **WsN-Viewer** needs Microsoft's “*App Installer*” for installation

1. Select “Windows => Settings => Apps => Apps & features”
2. Check if *App Installer* is listed as installed app
3. If *App Installer* is **not** installed:
 - Open *Microsoft Store* from the start menu
 - Search for “*App-Installer*”
 - Install the “*App-Installer*”
(Follow the instructions)



Hints:

- “*App-Installer*” is available since Windows 10, 1803!
- If the “*Microsoft Store*” is not available, contact Your IT administrator!

WsN-Viewer – Quick Installation Guide

Company Information

Document No: 2361

Approval Date: 06.12.2022

The reproduction, distribution and utilization of this document as well as the communication of its contents to others without explicit authorization is prohibited. Offenders will be held liable for the payment of damages. All rights reserved in the event of the grant of a patent, utility model or design. The contents of this edition have been checked with great care. However, errors cannot be fully excluded. Subject to technical change without notice.

asanetwork GmbH	© AxoNet Software GmbH
Gewerbestraße 8 87787 Wolfertschwenden Deutschland Fon: +49 (8334) 8980841 Mail: info@workshop-net.net Web: www.workshop-net.net	Osianderstraße 2/1 73230 Kirchheim unterm Teck Deutschland Fon: +49 (7021) 735600 Mail: info@axonet.de Web: www.axonet.de